

4-23. library.path is not available

library.path is not available

- : i-OLAP Server 7 (AUD7), i-OLAP Server 6 (AUD6)

- Olap

Step 1. Admin > i-OLAP >

{Context Path}/WEB-INF/classes/matrix application.conf library.path

Step 2. library.path library ({Context Path}/WEB-INF/lib)

{Context Path} Admin > .

library.path

library.path = {Context Path}/WEB-INF/lib

*application.conf - Windows 메모장

파일(F) 편집(E) 서식(O) 보기(V) 도움말(H)

OLAP configuration

Server configuration

application.name=olap_play

#i-BIG URL (Option)

ibig.path=http://127.0.0.1:9200/services/ibig.svc

library.path=C:/AUDPlatform_7/matrix/WEB-INF/lib

#i-AUD Service URL (Option)

#studio.url=http://127.0.0.1:8080/matrix/servlet/Studio.maf

java Option

daemon.xms=-Xms1G

daemon.xmx=-Xmx3G

java bit mode (-d32|-d64)

daemon.bit.mode=

##daemon.timeout = 30(minute)

daemon.timeout=20

Daemon Instance Max Count

daemon.instance.mcnt=5

Cache folder

##cache.folder=D:/reports

Column Limit Size

column.limit = 16000

Record Limit Size (0=unlimit)

record.limit = 3000000

Step 3. i-OLAP