

4.AUD ?

Page No. 97623772

: / :

: AUD 7.0.400.

AUD 7.0 service_api.properties matrix.security.token.expire.timeout.min () .

AUD 7

1. service_api.properties

1. service_api.properties
 - a. service_api.properties PathAdmin > > service_api.properties Path
 - i. service_api.properties
 - b. a
{CONTEXTPATH}/WEB-INF/classes/framework/service/service_api.properties
matrix.prop.location=
 - i. true
matrix.prop.location.path service_api.properties
 - ii. false
{CONTEXTPATH}/WEB-INF/classes/framework/service/service_api.properties
2. service_api.properties
 - a. matrix.security.token.expire.timeout.min
 - i. Token timeout (AccessToken expire)
 - ii.
 - b. matrix.jwtAccessTokenExpirationMs
 - i. Access Token Expiry time
 - ii. (5 = 300000)
- 3.

2. Admin

1.
 - a. Admin > > PORTAL > >
2. (SESSION_EXTEND_TIMEOUT)
 - a. (updateSession.jsp)
 - b. : Admin > > PORTAL > > SESSION_EXTEND_TIMEOUT >
 - c. :

--AS-IS --

: AUD 6

i-PORTAL

MATRIX .

1. WAS
2. matrix.properties


- 1 WAS
- 2 matrix.properties .

1) WAS

. WAS Tomcat .

) ..Tomcat / conf / web.xml

```
<session-config>
  <session-timeout>30</session-timeout>
</session-config>
```



```
573     <url-pattern>*/</url-pattern>
574 </filter-mapping>
575 ->
576
577 <!-- The mapping for the SSI Filter -->
578 <!--
579     <filter-mapping>
580         <filter-name>ssi</filter-name>
581         <url-pattern>*.shtml</url-pattern>
582     </filter-mapping>
583 ->
584
585
586 <!-- ===== Default Session Configuration ===== -->
587 <!-- You can set the default session timeout (in minutes) for all newly -->
588 <!-- created sessions by modifying the value below. -->
589
590 <session-config>
591     <session-timeout>30</session-timeout>
592 </session-config>
593
```

2) matrix.properties

```
. : ..Matrix Server / WEB-INF / classes / matrix / matrix.properties
```

```
matrix.responsecharset="utf-8"
matrix.requestcharset="utf-8"

matrix.installername="MTXInstaller.CAB#version=1,0,0,40"
matrix.notsafer="true"
matrix.mydocument="true"

## Configuration Management setting
matrix.selfcm="true"
matrix.configmgt="1"
matrix.filebackup="0"

matrix.pwdencrypt= "2"

##matrix.selfcmcrypt="true"
##matrix.scheduler="false"
##matrix.ext.usedbsecurity="true"
##matrix.ext.drmflag="1"
##matrix.usemasking="true"
##matrix.sessiontime="3600" |
```

3600(1) .

